

AMSOsram ICC Software Manual

Spikes Casting Dispensing Machine

Date: R3, 12Jun2025

Introduction

The core principle of ICC is to dispense randomly selected units for an initial test, analyse the results, and adjust the dispensing volume for the remaining units to achieve the desired test outcome.

In **Pass 1**, a predefined set of units from the Panel is dispensed with an initial volume. The Panel is then tested, and the ICC Server processes the test data to compute the necessary volume adjustments.

In **Pass 2**, the remaining units are dispensed using the newly determined volume to optimize the test results.

Definitions

Input File	Input File in xml format to retrieve from Input Folder to obtain initial volume. The file sample as in Appendix.
Output File	Output File in text file format located in Output Folder to retrieve new volume. The file sample as in Appendix.
Lot File	Lot File in text file format located in Lot Folder to retrieve panel in lot information. It contains all the Panel ID of the lot. The file sample as in Appendix.
Input Folder	Configurable Directory. The location to retrieve Input File .
Output Folder	Configurable Directory. The location to retrieve Output File .
Lot Folder	Configurable Directory. The location to retrieve Lot File .
Panel ID	The ID for the Panel, scanned or manual entry by READ_ID command.
Pass 1 Panel ID list	A collection of Panel IDs stored locally that has been dispense as Pass 1.
Pass 2 Panel ID list	A collection of Panel IDs stored locally that has been dispense as Pass 2.

Normal Run Condition

Process/Condition	Description
Lot Entry.	Select Lot Entry . <i>Refer to Lot Entry.</i> Scan in lot information. Select Start Lot . <i>Recipe name of {11 SERIES} will be automatically loaded.</i>
If Recipe load fail.	Prompt error "Recipe not found or load fail". <i>User needs to manually dispose the Panel.</i>
Load magazine.	Load magazine.
Start operation.	Select Start .

Run Panel

Process/Condition	Description
Panel loading.	Load Panel to Pro Station .
	Scan Panel ID .
	Cross check local Pass 2 Panel ID list . If Panel ID exist,
Pass 2 Panel ID exists	Prompt error "Panel ID has completed Pass 2".

	<i>User needs to manually dispose the Panel.</i>
Pass 2 Panel ID do not exist.	Cross check local Pass 1 Panel ID list .
Pass 1 Panel ID exists	Goto Run Pass 2 .
Pass 1 Panel ID do not exist.	Goto Run Pass 1 .

Run Pass 1

Process/Condition	Description
Input File check.	Check for Input File .
Input File do not exist.	Prompt error "Input File is not found." <i>User needs to manually dispose the Panel.</i>
Input File exist.	Retrieve Input File . Decode the initial volume by element <i>InitialDispenserSetting="0.8"</i> . Update the volume as Current Dispense Volume .
Unit selection.	Select PreMap 1. <i>PreMap 1 is the selected Pass 1 units to be dispensed.</i>
Dispense.	Run dispense.
Complete.	Unload Panel.

Run Pass 2

Process/Condition	Description
Output File check.	Check for Output File .
Output File do not exist.	Prompt error "Output File is not found." <i>User needs to manually dispose the Panel.</i>
Output File exist.	Retrieve Output File . Check for PanelID .
PanelID do not exist.	Prompt error "PanelID is not found." <i>User needs to manually dispose the Panel.</i>
PanelID exist. Update new volume.	Decode the new volume of PanelID . Update the new volume as Current Dispense Volume . <i>If multiple similar PanelID exist, the last PanelID of the list will be applied.</i>
Unit selection.	Select PreMap 2. <i>PreMap 2 is the selected Pass 2 units to be dispensed.</i>
Dispense.	Run dispense.
Complete.	Unload Panel.

Run Condition – No Lot Entry

When a panel is loaded without Lot Entry, it will be processed manually. The following differences apply compared to standard processing:


1. The initial volume will be based on the Z_PATH default Nett Volume setting.
2. No Input File or Output File checking or updates of dispense value.

Process	Lot Entry	No Lot
READ_ID	✓ (when enabled) Panel ID is used for volume feedback.	✓ (when enabled) Panel ID is not used.
OSRAM_ICC	✓ Checking of Input File and Output File.	✗
DOT_ZPATH	✓ Volume from Input File and Output File are updated.	✓ Default Nett Volume will be used.

Execution Comparison


Lot Entry

Lot Entry feature needs to be enabled at Options-Process. Select type **OsramICC**.



The screenshot shows the 'Options' dialog box with the 'Process' tab selected. Under the 'Lot Settings' section, the 'Enable Lot Entry' checkbox is checked, and the 'Type' dropdown menu is set to 'OsramICC'.

User Interface to enter Lot Data. The first 4 fields, **EMPLOYEE ID**, **LOT NUMBER**, **11 SERIES** and **DA START NUMBER** are compulsory while 4 fields are user definable.



The screenshot shows the 'frm_LotEntryOsramEMos' form. It has five input fields labeled (1) EMPLOYEE ID, (2) LOT NUMBER, (3) 11 SERIES, (4) DA START NUMBER, and (5) FIELD NAME 5. Below the fields are four buttons: EDIT, START LOT, END LOT, and CLOSE.

Field	Description	Usage
EMPLOYEE ID	Enter Employee ID	Record purposes only.
LOT NUMBER	Lot Number on traveller	Filename of Output File . Filename of Lot File .
11 SERIES	11 Series on traveller	Used to Auto Load Device. Part of filename of Input File .
DA START NUMBER	DA Start Number on traveller	Part of filename of Input File .
Field5 (optional)	User configurable field.	Record purposes only.
Field6 (optional)	User configurable field.	Record purposes only.
Field7 (optional)	User configurable field.	Record purposes only.
Field8 (optional)	User configurable field.	Record purposes only.

File Logistics

Dispenser Setup

[Head Calibration](#)
[Head Cal Setting](#)
[Teach Needle](#)
[Disp Control](#)
[Clean Purge](#)
[Maintenance](#)
[Weight](#)
[Options](#)
[Custom](#)

Volume Offset

Protocol: 7 : OSRAM_ICC

Input Path: c:\OsramICC

Output Path: c:\OsramICC

Lot Path: c:\OsramICC

Input File
Load

Output File
Input Path
Load & Lookup

Local PanelID List
Load
Save
Edit Pass1
Edit Pass2

Lot File
Load

Update & Check
Test

Input Map

Protocol: 0 : None

Idle
Jog
Save
Close

Item	Description	Usage
Protocol	Select Volume adjustment Protocol.	Applies Osram ICC volume adjustment.
Input Path	Define the Input Path of Input Files.	Location to retrieve the Input Files.
Output Path	Define the Output Path of Output Files.	Location to retrieve the Output Files.
Update & Check	Update and check Input Path and Output File.	Verify the path validity. Brief colour indicators.
Input File – Load	Load the current Input File.	Test load the current input file and display the volume information. The Lot Entry must be entered prior to the test.
Output File – Load	Load the Panel ID Output file.	Test load the Panel ID Output File to memory.
Output File – Lookup	Lookup the Panel ID volume information.	Test lookup of the Panel ID and display the volume information.
Lot File – Load	Load the lot Panel ID list.	Test loading of the lot file that contains the Panel ID list.
Local PanelID - Load	Load Pass1 and Pass2 local Panel ID list.	Test load the local Panel ID list. The list will store up to 100 last processes Panel ID.
Local PanelID - Save	Save Pass1 and Pass2 local Panel ID list.	Test save the local Panel ID list. The list will store up to 100 last processes Panel ID.
Edit Pass1, Edit Pass2	Open the local Pass1 or Pass2 text file.	Edit the local Panel ID list.
Test	Test OsramICC function.	Test OSRAM_ICC function for volume settings.

DOT_ZPATH Command

019 DOTS_ZPATH

Head No3Dispense

Model No0Edit

Position

-1.924,-0.888SetGoto

Point TL

Disp Gap

Down Wait

Disp

End Gap

D1

Speed

D2

SpeedF

D3

Speed

D4

Point BR

Disp Gap

Disp

End Gap

Post Wait

Disp Gap (mm)*0.3

End Gap (mm)0.3

Ret Gap (mm)*3

AccelDecel (mm/s3)*2500.0

Speed (mm/s)*8.0

SpeedF (mm/s)*30.0

Down Wait (ms)*10

Post Wait (ms)*100

Nett Volume

Head2Head 1

D1, Dot 1 (%)25

D2, Dot 2 (%)25

D3, Dot 3 (%)25

D4, Dot 4 (%)25

Default (ul)0.3680.367

Current (ul)0.3680.367

OK

Cancel

000 DOTS_ZPATH

Head No3Dispense

Model No0Edit

Position

0.000,0.000SetGoto

Point TL

Disp Gap

Down Wait

Disp

End Gap

D1

Speed

D2

Speed2

D3

Speed3

D4

Point BR

Disp Gap

Disp

End Gap

Post Wait

Disp Gap (mm)*0.2

End Gap (mm)0.5

Ret Gap (mm)*4

AccelDecel (mm/s3)*12.0

Speed (mm/s)*10.0

Speed 2 Ratio1

Speed3 (mm/s)*10.0

Down Wait (ms)*10

Post Wait (ms)*20

Tail Off

Square

Volume

Head2Head 1

D1, Dot 1 (%)25

D2, Dot 2 (%)25

D3, Dot 3 (%)25

D4, Dot 4 (%)25

Default Nett (ul)0.0000.000

Current Nett (ul)0.4000.400

BackSuck (ul)0.1000.100

OK

Cancel

Item	Description
Head No	Select Head Execution 0 – none 1: Head 1 only (Single Head) 2: (not support) 3: Head 1 and Head 2.
Model No	Select Model No to applies.
Edit	Edit Model.
Dispense	Options to enable Dispense
TL Set/Goto	Set and Goto Top Left corner of the pattern path.
BR Set/Goto	Set and Goto Bottom Right corner of the pattern path.
Disp Gap	Define the Needle distance from the detect height for dispense.
End Gap	Define the Needle distance from the detect height after dispensing of each dot.
Ret Gap	Define the Needle distance from the detect height after completing of the unit dispensing.
Accel/Decel	Define acceleration and deceleration of the path.
Speed	Define speed 1.
Seepd 2 Ratio	The ratio of Speed 2 referencing Speed 1.
Speed 3	Define speed 3.
Down Wait	Time to wait before path dispensing.
Post Wait	Time to wait after path dispensing.
Volume	Display and adjust the default
Default Nett	Nett volume.
Volume	Display and adjust the current
Current Nett	Nett volume. <i>Nett Volume = Disp Volume – Backsuck Volume</i>
Volume	Display and adjust the BackSuck
BackSuck	volume.
D1-D4	Define the percentage distribution of each dot.

000	LAYOUT	[0] Unit M CR(28,28) Cistr CR(M1,M1) YFU
001	READ_ID	[0]
002	OSRAM_ICC	
003	FOR_LAYOUT	[0]
004	USE_MAP	
005	DO_REF	[0] Board P1(-89.516,1.483) P2(1.485,-89.496)
006	END_LAYOUT	[0]
007	FOR_LAYOUT	[0]
008	USE_MAP	
009	USE_REF	[0]
010	DO_HEIGHT	[0] Board Least Square Fit 8 Point(s)
011	END_LAYOUT	[0]
012	FOR_LAYOUT	[0]
013	PP_FILL	Cond1,14,0
014	CLEAN	Cond1,2,0 Cond2,8,0 (Auto) Count 1, Time 1ms, Delay 700ms
015	PURGE	Cond1,2,0 (Auto) Count 1, Time 20ms, Delay 900ms, PVT 8
016	USE_MAP	
017	USE_REF	[0]
018	USE_HEIGHT	[0]
019	DOTS_ZPATH*	
020	UNIT_COMPL...	
021	END_LAYOUT	[0]
022	BD_READY	

Place READ_ID after LAYOUT to execute ID Read.

Place OSRAM_ICC after READ_ID to execute OsramICC flow.

Sample for Program for ICC

Panel List Display

Panel List on auto window will display the Panel ID of the lot and its status. The status are based on local Pass 1 and Pass 2 files.

Condition:

1. Lot is started and Active.
2. OSRAM_ICC mode is selected.
3. The lot file exists and contains correct list of Panel IDs.
4. The status are updated according to local **Pass 1 and Pass 2 Panel ID list**

Run Info	Manual	Map	Disp Tools	SecsGem	Panel List	
JMU00MZU		JMU00MYF				
JMU00MZS		JMU00MZT				
JMU00MYE						
JMU00MYC						
JMU00MZY						
JMU00MZW						
JMU00MZ7						
JMU00MYH						

Color Status

None: Panel ID is not processed.

Yellow: Panel ID has started **Pass 1**.

Green: Panel ID has started **Pass 2**.

Panel ID	Pass1	Pass2
JMU00MZU	Yes	Yes
JMU00MZS	Yes	Yes
JMU00MYE	Yes	Yes
JMU00MYC	Yes	No
JMU00MZY	Yes	No
JMU00MZW	Yes	No
JMU00MZ7	No	No
JMU00MYH	No	No
JMU00MYF	No	No
JMU00MZT	No	No

Appendix

Sample Input File

Filename: {Input Folder}\{11 SERIES}_{DA START NUMBER}__.xml

Input folder using Map Drive is accessibility must be provided by local IT security policy. Otherwise use the full Universal Naming Convention(UNC) Path for the network folder name.

Note:

- underscore between {11 SERIES} and {DA START NUMBER}
- ends with 2 underscores.

Example: {Input Folder}\11108864_L15NSWDL4GWCSSRM3.PMN4P1A535K2M2700__.xml

Example content:



```
<SteeringSettings xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:xsd="http://www.w3.org/2001/XMLSchema" xmlns="http://www.osram-os.com/steering/config"
  ProductName="Demon Poseidon BREE 3000K">
  <LogFileLocation>\\int.osram-light.com\Net-klm\!Apps\Casting\OSLONSquare\LLC_LogFiles\</LogFileLocation>
  <PanelSize RowMax="28" ColMax="28"/>
  <TargetSettings InitialDispenserSetting="0.8" ColorSpace="CIE2DegreeCxCy" TargetCxCyDistance="0.4" TargetPathAngle="22"> </TargetSettings>
  <ControllerSettings ControllerModule="ComixBasedController" PathLengthOffset="0.01" FloatingLength="2">
    <Converters>
      <Converter Name="QL905" InitialWeightPercent="3" Group="1" AllowVariation="true"/>
      <Converter Name="QL904" InitialWeightPercent="3" Group="1" AllowVariation="true"/>
      <Converter Name="L167" InitialWeightPercent="3" Group="2" AllowVariation="true"/>
    </Converters>
  </ControllerSettings>
</SteeringSettings>
```

```
<SteeringSettings xmlns:xsi="http://www.w3.org/2001/XMLSchema-instance" xmlns:xsd="http://www.w3.org/2001/XMLSchema" xmlns="http://www.osram-
os.com/steering/config" ProductName="Demon Poseidon BREE 3000K">
  <LogFileLocation>\\int.osram-light.com\Net-klm\!Apps\Casting\OSLONSquare\LLC_LogFiles\</LogFileLocation>
  <PanelSize RowMax="28" ColMax="28"/>
  <TargetSettings InitialDispenserSetting="0.8" ColorSpace="CIE2DegreeCxCy" TargetCxCyDistance="0.4" TargetPathAngle="22"> </TargetSettings>
  <ControllerSettings ControllerModule="ComixBasedController" PathLengthOffset="0.01" FloatingLength="2">
    <Converters>
      <Converter Name="QL905" InitialWeightPercent="3" Group="1" AllowVariation="true"/>
      <Converter Name="QL904" InitialWeightPercent="3" Group="1" AllowVariation="true"/>
      <Converter Name="L167" InitialWeightPercent="3" Group="2" AllowVariation="true"/>
    </Converters>
  </ControllerSettings>
</SteeringSettings>
```

Sample Output File

Filename: {Output Folder}\{Lot Number}.txt

Example: {Output Folder}\LOTABCD.txt

Input folder using Map Drive is accessibility must be provided by local IT security policy. Otherwise use the full Universal Naming Convention(UNC) Path for the network folder name.

Content:

The file contains list of lines of Panel ID, Dispense 1 and Dispense 2 volume semi-colon (;) delimited.

Panel;Dispenser1;Dispenser2

{Panel ID 1};{Head 1 Volume 1};{Head 2 Volume 2}

{Panel ID 2};{Head 1 Volume 2};{Head 2 Volume.2}

...

{Panel ID n};{Head 1 Volume n};{Head 2 Volume.n}

Example content:

Panel;Dispenser1;Dispenser2

JMC1234;1.1112;1.1016

JMC1235;1.1242;1.0735

JMC1236;1.1034;1.1143

JMC1237;1.1143;1.1023
JMC1234;1.1200;1.1200

Sample Lot File

Filename: {Lot Folder} \ {Lot Number}.txt

Example: {Lot Folder} \ KGG4113.txt

Lott folder using Map Drive is accessibility must be provided by local IT security policy. Otherwise use the full Universal Naming Convention(UNC) Path for the network folder name.

Content:

The file contains list of lines of Panel ID

{Panel ID 1}

{Panel ID 2}

...

{Panel ID n}

Example content:

JMU00MZU

JMU00MZS

JMU00MYE

JMU00MYC

JMU00MZY

JMU00MZW

JMU00MZ7

JMU00MYH

JMU00MYF

JMU00MZT

Last Known Settings

Input File Path: \\int.osram-light.com\!Apps\Casting\OSLONSquare\Tools\OslonDC\setting_DC

Output File Path: \\int.osram-light.com\!Apps\Casting\OSLONSquare\Tools\OslonDC\Dispense_Wgt

Lot File Path: \\int.osram-light.com\!Apps\Casting\OSLONSquare\Tools\OslonDC\Panel_ID

Revision

Rev	Date	Author	Description
0	20250320	NSW KN	Initial Version
1	20250329	NSW KN	Change PanelID to PanelID Added DOT_ZPATH Command, File Logistics
2	20250415	NSW KN	Added Last Known Settings.
3	20250612	NSW KN	Added Lot File support.

End of document.